




The Home screen provides the following functions:

- Displays the robot's status.
- Shows the current joint angles.
- Allows the user to stop the robot.
- Enables navigation to other screens.




The Control screen provides the following functions:

- Enables the user to move the robot's end effector to a specified XYZ coordinate.
- Allows the user to adjust the robot's joints to specific angles.
- Provides an option to set the robot's home position.
- Allows the user to move the robot to its home position.

Move To
XYZ







12:00 

X: Y: Z:

RX: RY: RZ:

Execute

 Home  Control  Status  Settings

Input the desired XYZ coordinates and rotation, then press **Execute**. The robot will move to the specified position if it is within its reachable range.

Move To
Angles



12:00 

J1 J2 J3

J4 J5 J6

Execute

 Home  Control  Status  Settings

Input the desired joint angles, then press **Execute**. The robot will move to the specified angles if they are within the allowable joint limits.


CALIBRATE
HOME



Select the joint you want to move from the right side. Adjust the joint position, and when the arrows align, press **Calibrate** to set a new home position.

HOME



Pressing the **Home** button will command the robot to move to its home position.




Pressing **Joint** will display joint angles, status, limits, etc.

Pressing **Motor** will display motor status, speed, acceleration, etc.

Pressing **Encoder** will display the encoder status, joint angles read from the encoder, etc.



Here, you can connect the robot to WiFi, enabling remote control and access to the robot's status.



Here, you can adjust the touch screen brightness using the slider.

In the **Robot Settings**, users can adjust the robot's speed, acceleration and deceleration.